BIOS Release Notes Form

Supermicro disclaims all express and implied warranties, including without limitation, the implied warranties of merchantability, fitness for a particular purpose, and non-infringement, as well as any warranty arising from course of performance, course of dealing, or usage in trade. All products, computer systems, dates, and figures specified are preliminary based on current expectations, and are subject to change without notice. Supermicro and the Supermicro logo are trademarks of Super Micro Computer, Inc. in the U.S. and/or other countries. Copyright © 2018 Super Micro Computer, Inc. All rights reserved.

Product Name	H12DSU-iNR
Release Version	2.3
Release Date	10/20/2021
Previous Version	2.0
Update Category	Critical
Dependencies	None
Important Notes	BIOS_H12DSUR-1C4B_20211020_2.3_STDsp.bin - BIOS image BIOS_H12DSUR-1C4B_20211020_2.3_STDsp.zip - BIOS image and flash utility package
	1. Changed BIOS revision to 2.3.
	2. Added Redfish/SUM Secure Boot feature and updated OOB for
	secure boot and reserve key.
	3. Added support in SUM to upload and delete HTTPS TLS certificate.
	(The default is to enable the TOKEN "Sum_UploadTlsKey_SUPPORT.")
Enhancements	4. Set the BIOS setting "Relaxed Ordering default" to Enabled.
	5. Updated AGESA RomePI to 1.0.0.C.
	6. Exposed the BIOS setting "Enhanced Preferred IO Mode".
	7. Updated AGESA MilanPI to 1.0.0.6.
	8. Updated Milan B0/B1 stepping CPU microcode and Milan-X B2
	stepping CPU microcode to patch Erratum #1381 Processor May Hang
	When Coherency Probe Hits Instruction Cache
	9. Enabled SUM to modify AMD CBS settings.

	10. Fixed the BMC Redfish Host Interface named as ethX when CDN
	was disabled case under Linux OS.
	11. Disabled Legacy/EFI iSCSI support.
	12. Exposed the BIOS setting "BankGroupSwapAlt", "SEV-SNP
	Support", "Enhanced Preferred IO Mode" and "Root Complex
	0x00~0xE0 LCLK Frequency".
	13. Changed the default of "Wait For "F1" If Error" to Disabled.
New features	N/A
Fixes	N/A

Release Notes	from Previous	Release	s)
----------------------	---------------	---------	----

2.0	(06/18/202	1
-----	------------	---

First release.